

2/5/10 Lecture 10 outline

- Renormalization. The input to the functional integral is the “bare” lagrangian. It is not physically observable, because we observe quantities like mass, charge, etc. with all the quantum corrections included. Write the lagrangian for the bare fields as:

$$\mathcal{L}_B = \frac{1}{2}\partial_\mu\phi_B\partial^\mu\phi_B - \frac{1}{2}m_B^2\phi_B^2 - \lambda_B\frac{1}{4!}\phi_B^4.$$

The bare field is related to the physical one by $\phi_B \equiv Z_\phi^{1/2}\phi$. We can view this as

$$\mathcal{L}_B = \mathcal{L}_{phys} + \mathcal{L}_{c.t.}$$

where

$$\mathcal{L}_{phys} = \frac{1}{2}\partial_\mu\phi\partial^\mu\phi - \frac{1}{2}m^2\phi^2 - \lambda\frac{1}{4!}\phi^4$$

involves the physical field, mass, coupling constant. What’s left are the counterterms:

$$\mathcal{L}_{c.t.} = \frac{1}{2}(Z - 1)\partial_\mu\phi\partial^\mu\phi - \frac{1}{2}(m_B^2Z - m^2)\phi^2 - (\lambda_BZ^2 - \lambda)\frac{1}{4!}\phi^4.$$

Define $\delta_Z \equiv Z - 1$, $\delta m = m_B^2Z - m^2$, $\delta\lambda = \lambda_BZ^2 - \lambda$. There are extra diagram contributions for these corrections.

There is a line (like the propagator) with an insertion of the counterterm, which gives a factor of $i(p^2\delta_Z - \delta_m)$. There is a new vertex with a factor of $-i\delta\lambda$. These new diagrams count as having one loop factor (one factor of \hbar).

- Among other things, these corrections cancel the divergences. E.g. δm adds to Π' , so pick the additive contribution to cancel the divergence in Π' ; likewise, $\delta\lambda$ adds to effective λ obtained from $\tilde{\Gamma}^{(4)}$, so

$$\delta_m = \frac{\lambda m^2}{16\pi^2} \frac{1}{\epsilon} + \text{finite} + \mathcal{O}(\lambda^3).$$

$$\delta\lambda = 3\frac{\lambda^2}{16\pi^2} \frac{1}{\epsilon} + \text{finite} + \mathcal{O}(\lambda^4).$$

To one loop, $\delta_Z = 0 + (\text{finite})$, because $\Pi'(p^2)$ is independent of p^2 .

- What to do about the finite parts is a choice that we can make, our renormalization prescription. We have to define what we’re calling the physical mass and coupling. One choice is to define the mass to be the pole of the full propagator (sum of all connected

diagrams), $D(p) = i/\tilde{\Gamma}^{(2)}$, and to define the physical field so that the residue of the pole is i . This means

$$\Pi'(m^2) = 0, \quad \frac{d\Pi'}{dp^2}\Big|_{p^2=m^2} = 0, \quad \tilde{\Gamma}^{(4)}\Big|_{s=4m^2} = -\lambda$$

where the last condition is our definition of physical λ . With this choice, we have

$$\delta_m = +\frac{\lambda m^2}{32\pi^2} \left(\frac{2}{\epsilon} - \log \frac{m^2}{4\pi\mu^2} + 1 - \gamma \right)$$

to this order, and so, to this order they combine to give

$$\Pi'(p^2) = 0.$$

We also have $\delta Z = 0$ and $\delta\lambda$ is such that now

$$\tilde{\Gamma}^{(4)} = -\lambda + \frac{\lambda^2}{32\pi^2} (A_1(s) + A_1(t) + A_1(u) - A_1(4m^2) - 2A_1(0)).$$